



OBSD.RU

[Home](#)

Xorg.conf для Acer TravelMate 2303LC

[printable page](#)

Дмитрий Аленичев

dmesg

```
OpenBSD 3.8 (GENERIC) #138: Sat Sep 10 15:41:37 MDT 2005
deraadt@i386.openbsd.org:/usr/src/sys/arch/i386/compile/GENERIC
cpu0: Intel(R) Celeron(R) M processor 1500MHz ("GenuineIntel" 686-class) 1.50 GHz
cpu0:
FPU,V86,DE,PSE,TSC,MSR,MCE,CX8,SEP,MTRR,PGE,MCA,CMOV,PAT,CFLUSH,ACPI,MMX,FXSR,SSE,SSE2,TM,SBF
real mem = 258449408 (252392K)
avail mem = 228941824 (223576K)
using 3180 buffers containing 13025280 bytes (12720K) of memory
mainbus0 (root)
bios0 at mainbus0: AT/286+(66) BIOS, date 06/29/04, BIOS32 rev. 0 @ 0xfd540
pcibios0 at bios0: rev 2.1 @ 0xfd540/0xac0
pcibios0: PCI IRQ Routing Table rev 1.0 @ 0xfdd20/160 (8 entries)
pcibios0: PCI Interrupt Router at 000:31:0 ("Intel 82371FB ISA" rev 0x00)
pcibios0: PCI bus #2 is the last bus
bios0: ROM list: 0xc0000/0xcc00! 0xcd000/0x1800 0xdf800/0x800! 0xe0000/0x4000!
cpu0 at mainbus0
pci0 at mainbus0 bus 0: configuration mode 1 (no bios)
pchb0 at pci0 dev 0 function 0 "Intel 82852GM Hub-PCI" rev 0x02
"Intel 82852GM Memory" rev 0x02 at pci0 dev 0 function 1 not configured
"Intel 82852GM Configuration" rev 0x02 at pci0 dev 0 function 3 not configured
vga1 at pci0 dev 2 function 0 "Intel 82852GM AGP" rev 0x02: aperture at 0xe8000000, size 0x8000000
wsdisplay0 at vga1 mux 1: console (80x25, vt100 emulation)
wsdisplay0: screen 1-5 added (80x25, vt100 emulation)
"Intel 82852GM AGP" rev 0x02 at pci0 dev 2 function 1 not configured
uhci0 at pci0 dev 29 function 0 "Intel 82801DB USB" rev 0x03: irq 6
usb0 at uhci0: USB revision 1.0
uhub0 at usb0
uhub0: Intel UHCI root hub, rev 1.00/1.00, addr 1
uhub0: 2 ports with 2 removable, self powered
uhci1 at pci0 dev 29 function 1 "Intel 82801DB USB" rev 0x03: irq 6
usb1 at uhci1: USB revision 1.0
uhub1 at usb1
uhub1: Intel UHCI root hub, rev 1.00/1.00, addr 1
uhub1: 2 ports with 2 removable, self powered
uhci2 at pci0 dev 29 function 2 "Intel 82801DB USB" rev 0x03: irq 6
```

usb2 at uhci2: USB revision 1.0
uhub2 at usb2
uhub2: Intel UHCI root hub, rev 1.00/1.00, addr 1
uhub2: 2 ports with 2 removable, self powered
ehci0 at pci0 dev 29 function 7 "Intel 82801DB USB" rev 0x03: irq 10
usb3 at ehci0: USB revision 2.0
uhub3 at usb3
uhub3: Intel EHCI root hub, rev 2.00/1.00, addr 1
uhub3: 6 ports with 6 removable, self powered
ppb0 at pci0 dev 30 function 0 "Intel 82801BAM Hub-to-PCI" rev 0x83
pci1 at ppb0 bus 1
bce0 at pci1 dev 2 function 0 "Broadcom BCM4401" rev 0x01: irq 6, address 00:c0:9f:87:e7:0e
bmtphy0 at bce0 phy 1: BCM4401 10/100baseTX PHY, rev. 0
cbb0 at pci1 dev 6 function 0 vendor "Texas Instruments", unknown product 0x8031 rev 0x00: irq 10
cardslot0 at cbb0 slot 0 flags 0
cardbus0 at cardslot0: bus 2 device 0 cacheline 0x8, lattimer 0x20
pcmcia0 at cardslot0
ichpcib0 at pci0 dev 31 function 0 "Intel 82801DBM LPC" rev 0x03: SpeedStep
pciide0 at pci0 dev 31 function 1 "Intel 82801DBM IDE" rev 0x03: DMA, channel 0 configured to compatibility, channel 1 configured to compatibility
wd0 at pciide0 channel 0 drive 0: <HTS424040M9AT00>
wd0: 16-sector PIO, LBA48, 38154MB, 78140160 sectors
wd0(pciide0:0:0): using PIO mode 4, Ultra-DMA mode 5
atapiscsi0 at pciide0 channel 1 drive 0
scsibus0 at atapiscsi0: 2 targets
cd0 at scsibus0 targ 0 lun 0: <QSI, CDRW/DVD SBW242C, UQ81> SCSI0 5/cdrom removable
cd0(pciide0:1:0): using PIO mode 4, Ultra-DMA mode 2
"Intel 82801DB SMBus" rev 0x03 at pci0 dev 31 function 3 not configured
auich0 at pci0 dev 31 function 5 "Intel 82801DB AC97" rev 0x03: irq 10, ICH4 AC97
ac97: codec id 0x43585430 (Conexant CX?????)
ac97: codec features reserved, headphone, 18 bit DAC, 18 bit ADC, No 3D Stereo
audio0 at auich0
"Intel 82801DB Modem" rev 0x03 at pci0 dev 31 function 6 not configured
isa0 at ichpcib0
isadma0 at isa0
pckbc0 at isa0 port 0x60/5
pckbd0 at pckbc0 (kbd slot)
pckbc0: using irq 1 for kbd slot
wskbd0 at pckbd0: console keyboard, using wsdisplay0
pms0 at pckbc0 (aux slot)
pckbc0: using irq 12 for aux slot
wsmouse0 at pms0 mux 0
pcppi0 at isa0 port 0x61
midi0 at pcppi0: <PC speaker>
spkr0 at pcppi0
sysbeep0 at pcppi0
npx0 at isa0 port 0xf0/16: using exception 16
biomask effd netmask effd ttymask ffff
pctr: 686-class user-level performance counters enabled
mtrr: Pentium Pro MTRR support

```
dkcsum: wd0 matches BIOS drive 0x80
root on wd0a
rootdev=0x0 rrootdev=0x300 rawdev=0x302
```

```
xorg.conf
```

```
Section "ServerLayout"
```

```
Identifier "X.org Configured"
Screen 0 "Screen0" 0 0
InputDevice "Mouse0" "CorePointer"
InputDevice "Keyboard0" "CoreKeyboard"
EndSection
```

```
Section "Files"
```

```
RgbPath "/usr/X11R6/lib/X11/rgb"
ModulePath "/usr/X11R6/lib/modules"
FontPath "/usr/X11R6/lib/X11/fonts/cyrillic/"
FontPath "/usr/X11R6/lib/X11/fonts/misc/:unscaled"
FontPath "/usr/X11R6/lib/X11/fonts/75dpi:unscaled"
FontPath "/usr/X11R6/lib/X11/fonts/100dpi:unscaled"
FontPath "/usr/X11R6/lib/X11/fonts/TTF/"
FontPath "/usr/X11R6/lib/X11/fonts/Type1/"
FontPath "/usr/local/lib/X11/fonts/mscorefonts/"
FontPath "/usr/local/lib/X11/fonts/ghostscript/"
FontPath "/usr/local/lib/X11/fonts/terminus/"
EndSection
```

```
Section "Module"
```

```
Load "dbe"
Load "extmod"
Load "glx"
Load "record"
Load "xtrap"
Load "freetype"
Load "type1"
EndSection
```

```
Section "InputDevice"
```

```
Identifier "Keyboard0"
Driver "kbd"
Option "XkbRules" "xfree86"
Option "XkbModel" "pc105"
Option "XkbLayout" "us,ru(winkeys)"
Option "XkbOptions" "grp:ctrl_shift_toggle"
EndSection
```

```
Section "InputDevice"
```

```
Identifier "Mouse0"
Driver "mouse"
Option "Protocol" "wsmouse"
Option "Device" "/dev/wsmouse"
Option "ZAxisMapping" "4 5"
```

EndSection

Section "Monitor"

Identifier "Monitor0"

VendorName "AUO"

ModelName "f06"

EndSection

Section "Device"

Option "Accel"

Option "SWcursor"

Identifier "Card0"

Driver "i810"

VendorName "Intel Corp."

BoardName "82852/855GM Integrated Graphics Device"

BusID "PCI:0:2:0"

EndSection

Section "Screen"

Identifier "Screen0"

Device "Card0"

Monitor "Monitor0"

DefaultDepth 24

SubSection "Display"

Viewport 0 0

Depth 24

EndSubSection

EndSection
